

COMET

```
*****  
* Comet version : 505.249   Date: 03/20/99   *  
* SYSGEN version: 99.021   *  
* Generated from OLD style CFG format.   *  
*****
```

[ENTERPRISE]

```
Name = Enterprise Name goes here;  
Adr1 = ;  
Adr2 = ;  
Adr3 = ;  
Phn# = ;  
Fax# = ;  
Attn = ;  
Internet Addr = ;
```

[SITE]

```
Name = Site Name goes here;  
Adr1 = ;  
Adr2 = ;  
Adr3 = ;  
Phn# = ;  
Fax# = ;  
Attn = ;  
Internet Addr = ;  
Network Dir = ;
```

```
* Server = N01, NLM, L, Comet_server_1;  
* Server = Nxx, IPX, R, 11223344: 556677889900;  
  
* CHANGE THE NEXT LINE FOR "NT" NETWORKS RUNNING SECURITY SERVER  
* AND REMOVE THE LEADING "*".  
  
Server = N01, TCP, L, 192.168.1.112;
```

[COMET SYSTEM OPTIONS]

```
First Partition      = P00;  
# of Partitions     = 8;  
First Terminal      = T00;  
# of Terminals      = 5;  
Time Slice Interval = 10;  
Fast Write Option   = YES;  
Ignore Error 44     = YES;  
Click on Task Break = NO;  
Background Priority = 0;  
European Numbers    = NO;  
Multi-USer Board Address = F;  
Single USer Plug Port # = 1;  
Enable LPT1 Interrupts = NO;  
Enable LPT2 Interrupts = NO;  
All Partitions Exp/Mem = NO;  
Clock Name          = CL1;  
# of File Descriptors = 120;  
Invoke Handle Banking = NO;  
Sliding Century     = 19;  
Sliding Year        = 40;  
Date Mode           = MMDDYYYY;
```

[CONSOLE SESSION OPTIONS]

```
Force 80 Column Mode = NO ;  
INSERT same as Qantel = NO ;  
C/R same as Qantel   = NO ;
```

COMET

Auto Increment Cursor = NO ;
Standard Keyboard I/O = YES;
Laptop Large Cursor = YES;
NumPad ENTER same as F10 = NO ;
Session 132 Bios Mode = 00;
4K Window Blocks/Session = 3;

[MULTI -USER BOARDS]

[TERMINALS]

[PRINTERS]

Printer = LP1, W , N, , \\PC1\HP LJ 5200-1: RAW, , ;
Printer = LP2, W , N, , \\PC3\HP Deskjet 815C: RAW, , ;
Printer = LP3, W , N, , \\PC1\HPLaserJ: RAW, ;
Printer = LP4, W , N, , \\PC2\LinePRT: RAW, , ;
Printer = LP5, W , N, , \\PC1\Acrobat Distiller, , ;
Printer = LP9, W , N, , Adobe PDF, , ;
Printer = LP6, L , N, , X:\DPAC\UTR\PRINTFIL.TXT, , ;
Printer = L98, L , N, , LPT2, , ;
Printer = L99, L , N, , LPT1, , ;
Printer = LF1, W , N, , CAPTURE FAX BVRP, , ;
Printer = LPH, H , N, , HTM, HTMLPTR, ;

[SPOOLERS]

Spool = SP1, \\pc1\PC1C\DPAC\SP1\
Spool = SP2, \\pc1\PC1C\DPAC\SP2\
;

[DIRECTORIES]

01 = C , \\PC1\PC1C\DPAC\REL\
02 = C , \\PC1\PC1C\DPAC\UTL\
03 = C , \\PC1\PC1C\DPAC\DSK\
04 = C , \\PC1\PC1C\DPAC\HLP\
05 = C , \\PC1\PC1C\DPAC\DOJ\
06 = C , \\PC1\PC1C\DPAC\UTR\
07 = C , \\PC1\PC1C\DPAC\SP1\
08 = C , \\PC1\PC1C\DPAC\SP2\
09 = C , \\PC1\PC1C\DPAC\WEB\
;

[GATEWAYS]

Gateway = 2, 0;
Gateway = 0, 0;
Gateway = 7, 0;
Gateway = 3, 0;

[INVALID CHARACTER TRANSLATION]

; Replaces =
~ ; Replaces /
` ; Replaces \
Q ; Replaces *
{ ; Replaces .
Q ; Replaces "
Q ; Replaces [

COMET

Q ; Repl aces +
Q ; Repl aces ;
Q ; Repl aces ,
Q ; Repl aces ?

*
* REMOVE THE "*" FOR EACH NODE BELOW FOR "SECURITY SERVER ONLY"
* IF RUNNING AN "NT" NETWORK WITH SECURITY SERVER.
*

[NODE]

Name = dpac1;
Desc = ;
Mi sc = ;
Path = ;
Phn# = ;
Fax# = ;
User = ;
Internet Addr = ;

* Server = Nxx, F; Database Server Only
Server = N01, SC; Security Server & Database Server
* Server = Nxx, SF; Both Security & Database Server

[COMET SYSTEM OPTIONS]

First Parti ti on = P00;
of Parti ti ons = 8;
Fi rst Termi nal = T00;
of Termi nal s = 5;

[CONSOLE SESSI ON OPTI ONS]

Sessi on = 000, P00, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 001, P01, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 002, P02, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 003, P03, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 004, P04, 5 , 1F, F1, 11, 11, 4E;

[PRI NTERS]

* Pri nter = LP5, L , N, , \\pc2\Acrobat Di sti ller, , ;

[SP00LERS]

Spool = SP1, \\pc1\DPAC\SP1\
Spool = SP2, \\pc1\DPAC\SP2\;

[NODE]

Name = dpac2;
Desc = ;
Mi sc = ;
Path = ;
Phn# = ;
Fax# = ;
User = ;
Internet Addr = ;

* Server = Nxx, F; Database Server Only
Server = N01, SC; Security Server & Database Server
* Server = Nxx, SF; Both Security & Database Server

COMET

```
[COMET SYSTEM OPTIONS]
  First Partition      = P08;
  # of Partitions     = 8;
  First Terminal      = T05;
  # of Terminals      = 5;
```

```
[CONSOLE SESSION OPTIONS]

  Sessi on = 005, P08, 5 , 1F, F1, 11, 11, 4E;
  Sessi on = 006, P09, 5 , 1F, F1, 11, 11, 4E;
  Sessi on = 007, P10, 5 , 1F, F1, 11, 11, 4E;
  Sessi on = 008, P11, 5 , 1F, F1, 11, 11, 4E;
  Sessi on = 009, P12, 5 , 1F, F1, 11, 11, 4E;
```

```
[PRINTERS]

*  Printer = LP1, L , N,           , LPT1, , ;
*  Printer = LP2, W , N,           , Epson LQ-570+ ESC/P 2: RAW, , ;
*  Printer = LP3, W , N,           , HP LaserJet 4L: RAW, , ;
*  Printer = LP9, L , N,           , X: \DPAC\UTR\PRINTFIL.TXT, , ;
```

```
[NODE]
  Name = dpac3;
  Desc = ;
  Mi sc = ;
  Path = ;
  Phn# = ;
  Fax# = ;
  User = ;
  Internet Addr = ;

*  Server = Nxx, F;           Database Server Only
  Server = N01, SC;         Security Server & Database Server
*  Server = Nxx, SF;        Both Security & Database Server
```

```
[COMET SYSTEM OPTIONS]
  First Partition      = P16;
  # of Partitions     = 8;
  First Terminal      = T10;
  # of Terminals      = 5;
```

```
[CONSOLE SESSION OPTIONS]

  Sessi on = 010, P16, 5 , 1F, F1, 11, 11, 4E;
  Sessi on = 011, P17, 5 , 1F, F1, 11, 11, 4E;
  Sessi on = 012, P18, 5 , 1F, F1, 11, 11, 4E;
  Sessi on = 013, P19, 5 , 1F, F1, 11, 11, 4E;
  Sessi on = 014, P20, 5 , 1F, F1, 11, 11, 4E;
```

```
[PRINTERS]

  Printer = LP2, L , N,           , LPT1, , ;
```

```
[NODE]
  Name = dpac4;
  Desc = ;
  Mi sc = ;
  Path = ;
  Phn# = ;
  Fax# = ;
  User = ;
  Internet Addr = ;
```

COMET

- * Server = Nxx, F; Database Server Only
- Server = N01, SC; Security Server & Database Server
- * Server = Nxx, SF; Both Security & Database Server

[COMET SYSTEM OPTIONS]

First Partition = P24;
of Partitions = 8;
First Terminal = T15;
of Terminals = 5;

[CONSOLE SESSION OPTIONS]

Session = 015, P24, 5, 1F, F1, 11, 11, 4E;
Session = 016, P25, 5, 1F, F1, 11, 11, 4E;
Session = 017, P26, 5, 1F, F1, 11, 11, 4E;
Session = 018, P27, 5, 1F, F1, 11, 11, 4E;
Session = 019, P28, 5, 1F, F1, 11, 11, 4E;

[NODE]

Name = dpac5;
Desc = ;
Misc = ;
Path = ;
Phn# = ;
Fax# = ;
User = ;
Internet Addr = ;

- * Server = Nxx, F; Database Server Only
- Server = N01, SC; Security Server & Database Server
- * Server = Nxx, SF; Both Security & Database Server

[COMET SYSTEM OPTIONS]

First Partition = P32;
of Partitions = 8;
First Terminal = T20;
of Terminals = 5;

[CONSOLE SESSION OPTIONS]

Session = 020, P32, 5, 1F, F1, 11, 11, 4E;
Session = 021, P33, 5, 1F, F1, 11, 11, 4E;
Session = 022, P34, 5, 1F, F1, 11, 11, 4E;
Session = 023, P35, 5, 1F, F1, 11, 11, 4E;
Session = 024, P36, 5, 1F, F1, 11, 11, 4E;

[NODE]

Name = dpac6;
Desc = ;
Misc = ;
Path = ;
Phn# = ;
Fax# = ;
User = ;
Internet Addr = ;

- * Server = Nxx, F; Database Server Only
- Server = N01, SC; Security Server & Database Server
- * Server = Nxx, SF; Both Security & Database Server

[COMET SYSTEM OPTIONS]

First Partition = P39;

COMET

of Partitions = 8;
First Terminal = T25;
of Terminals = 5;

[CONSOLE SESSION OPTIONS]

Session = 025, P39, 5 , 1F, F1, 11, 11, 4E;
Session = 026, P40, 5 , 1F, F1, 11, 11, 4E;
Session = 027, P41, 5 , 1F, F1, 11, 11, 4E;
Session = 028, P42, 5 , 1F, F1, 11, 11, 4E;
Session = 029, P43, 5 , 1F, F1, 11, 11, 4E;

[NODE]

Name = dpac7;
Desc = ;
Misc = ;
Path = ;
Phn# = ;
Fax# = ;
User = ;
Internet Addr = ;

- * Server = Nxx, F; Database Server Only
- * Server = N01, SC; Security Server & Database Server
- * Server = Nxx, SF; Both Security & Database Server

[COMET SYSTEM OPTIONS]

First Partition = P47;
of Partitions = 8;
First Terminal = T30;
of Terminals = 5;

[CONSOLE SESSION OPTIONS]

Session = 030, P47, 5 , 1F, F1, 11, 11, 4E;
Session = 031, P48, 5 , 1F, F1, 11, 11, 4E;
Session = 032, P49, 5 , 1F, F1, 11, 11, 4E;
Session = 033, P50, 5 , 1F, F1, 11, 11, 4E;
Session = 034, P51, 5 , 1F, F1, 11, 11, 4E;

[NODE]

Name = dpac8;
Desc = ;
Misc = ;
Path = ;
Phn# = ;
Fax# = ;
User = ;
Internet Addr = ;

- * Server = Nxx, F; Database Server Only
- * Server = N01, SC; Security Server & Database Server
- * Server = Nxx, SF; Both Security & Database Server

[COMET SYSTEM OPTIONS]

First Partition = P55;
of Partitions = 8;
First Terminal = T35;
of Terminals = 5;

[CONSOLE SESSION OPTIONS]

Session = 035, P55, 5 , 1F, F1, 11, 11, 4E;

COMET

Sessi on = 036, P56, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 037, P57, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 038, P58, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 039, P59, 5 , 1F, F1, 11, 11, 4E;

[NODE]

Name = dpac9;
Desc = ;
Mi sc = ;
Path = ;
Phn# = ;
Fax# = ;
User = ;
Internet Addr = ;

- * Server = Nxx, F; Database Server Only
- * Server = N01, SC; Security Server & Database Server
- * Server = Nxx, SF; Both Securi ty & Database Server

[COMET SYSTEM OPTIONS]

Fi rst Parti ti on = P63;
of Parti ti ons = 8;
Fi rst Termi nal = T40;
of Termi nal s = 5;

[CONSOLE SESSI ON OPTIONS]

Sessi on = 040, P63, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 041, P64, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 042, P65, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 043, P66, 5 , 1F, F1, 11, 11, 4E;
Sessi on = 044, P67, 5 , 1F, F1, 11, 11, 4E;

[END]